

Axxon Next Linux

1.

```
sudo dpkg-reconfigure axxon-next
```

2. ID Axxon-, . , Enter.

AxxonSoft Axxon Next Server Configuration
Leave this blank if you want this host to join an existing Axxon Next domain later or set to the KEEP to keep the value unmodified (if any).

Enter Axxon Next domain this host to proclaim.

KEEP

<0k>

3.

AxxonSoft Axxon Next Server Configuration
Name that uniquely identifies the installed server within Axxon Next domain. Leave this blank to have the value initialized from the host name or set to the KEEP to keep the value unmodified (if any).

Axxon Next server node name

DEBIAN

<0k>

4.

AxxonSoft Axxon Next Server Configuration
This port is used to determine base port of a TCP port span for Axxon Next applications. You may need to change this value if you run several instances of Axxon Next on the same host.

TCP port - base for Axxon Next TCP ports range

20111

<0k>

5.

AxxonSoft Axxon Next Server Configuration
In addition to the base port it determines TCP ports range used by Axxon Next applications.

Axxon Next TCP ports span

100

<0k>

6.

Axxon Next. :

- a. "0.0.0.0/0"
- b. "10.0.1.23/32,192.168.0.7/32"
- c. "127.0.0.1"

AxxonSoft Axxon Next Server Configuration
Comma-separated list of network interfaces in CIDR notation for AxxonSoft Axxon Next to listen on. Leave it empty if Axxon Next is supposed to use all available network interfaces.

List of network interfaces for Axxon Next to listen on.

<0k>

7. , NAT : "IP-1 DNS-1, IP-2 DNS-2".

AxonSoft Axxon Next Server Configuration
It may be used to specify public address for AxxonSoft Axxon Next when access a server working behind the NAT from outside. Appropriate port forwarding must be set up on the NAT itself in order to make this option work. Leave it empty if unsure or the server is not supposed to be accessed from outside.

Alternate primary network interfaces for Axxon Next to listen on.

<0k>

8. ().

AxonSoft Axxon Next Server Configuration

Log level for Axxon Next

0
ERROR
WARN
INFO
DEBUG
TRACE
ALL

<0k>

9.

AxonSoft Axxon Next Server Configuration
Enter host for AxxonSoft Axxon Next DB. Leave it empty or set to the KEEP to keep the value unmodified.

Axxon Next DB host

localhost

<0k>

10.

AxonSoft Axxon Next Server Configuration
Enter TCP-port which AxxonSoft Axxon Next DB listens to. Leave it empty or set to the KEEP to keep the value unmodified.

Axxon Next DB port

20110

<0k>

11. , ().

AxonSoft Axxon Next Server Configuration

Remove rotated logs older than <count> days

7

<0k>

12. . (.).

AxonSoft Axxon Next Server Configuration

Log maximum size (in megabytes)

10

<0k>